

Sent_30_Icu

Technical Reference

Project Release

Version 1.0.4

Authors	Denis Althapp
Status	Not Released

Document Information

History

Author	Date	Version	Remarks
virdea	[2015-06-22]	0.1.0	Initial version
virdea	[2015-06-23]	1.0.0	Ready for project release
virdea	[2015-07-13]	1.0.1	Small graphical changes
virdea	[2015-07-31]	1.0.2	Updated architecture with notification functions and new APIs
virdea	[2015-08-05]	1.0.3	Added InitMemory API
virdea	[2015-10-15]	1.0.4	Added diagnostic APIs

Reference Documents

No.	Source	Title	Version
[1]	SAE	J2716 SENT Specification	JAN2010
[2]	NXP	KMA215	[02/14]
[3]	Vector	CT_Sent_30_Icu	0.0.1
[4]	AUTOSAR	AUTOSAR_SWS_ICU_Driver.pdf	V3.3.0
[5]	AUTOSAR	AUTOSAR_SWS_DefaultErrorTracer.pdf	V4.2.1



Caution

We have configured the programs in accordance with your specifications in the questionnaire. Whereas the programs do support other configurations than the one specified in your questionnaire, Vector's release of the programs delivered to your company is expressly restricted to the configuration you have specified in the questionnaire.

Contents

1	Component History	6
2	Introduction.....	7
2.1	Architecture Overview	8
3	Functional Description	11
3.1	Use cases	11
3.2	Features	11
3.3	Limitations.....	12
3.4	Required knowledge	12
3.5	Behavior	13
3.5.1	Initialization	13
3.5.2	Processing of timestamps	13
3.5.2.1	MainFunction	14
3.5.2.2	IcuCallback	15
3.5.3	Fast channel processing	16
3.5.4	Slow channel processing	17
3.6	Error Handling.....	18
3.6.1	Development Error Reporting.....	18
4	Integration.....	19
4.1	Scope of Delivery.....	19
4.2	Required components.....	19
4.3	Initialization	19
4.4	Operation	19
4.5	Deinitialization.....	20
5	Configuration.....	21
5.1	MICROSAR configuration	21
5.1.1	ICU	21
5.1.2	PORT	22
5.2	Configuration with the supplied configuration module	22
5.2.1	Header file	22
6	API Description.....	24
6.1	Type Definitions	24
6.2	Global variables	25
6.3	Sent_30_Icu_Init.....	25
6.4	Sent_30_Icu_DeInit	26

6.5	Sent_30_Icu_IcuChannelCallback	26
6.6	Sent_30_Icu_MainFunction	27
6.7	Sent_30_Icu_GetVersionInfo	27
6.8	Sent_30_Icu_GetFastChannelData	27
6.9	Sent_30_Icu_GetSlowChannelData	28
6.10	Sent_30_Icu_GetDiagnosticValues	28
6.11	Sent_30_Icu_ResetDiagnosticValues	29
7	Glossary and Abbreviations	30
7.1	Glossary	30
7.2	Abbreviations	30
8	Contact.....	31

Illustrations

Figure 2-1	AUTOSAR 4.2 Architecture Overview	8
Figure 2-2	AUTOSAR 3.x Architecture Overview	9
Figure 2-3	Interfaces to adjacent modules of the Sent_30_Icu.....	10
Figure 3-1	Defined Use-cases for the Sent_30_Icu.....	11
Figure 3-2	Typical SENT frame (see [1]) – the nibble values are dependent on the delta between falling edges	12
Figure 3-3	MainFunction processing	14
Figure 3-4	ICU callback processing	15
Figure 3-5	Fast channel process.....	16
Figure 3-6	Slow channel process.....	17

Tables

Table 1-1	Component history.....	6
Table 3-1	Service IDs	18
Table 3-2	Errors reported to DET	18
Table 4-1	Static files	19
Table 4-2	Required components.....	19
Table 5-1	IcuChannel configuration	21
Table 5-2	PORT attributes for the sent input.....	22
Table 5-3	Sent_30_Icu_Cfg.h configuration items	23
Table 6-1	Sent_30_Icu_FastDataType	24
Table 6-2	Sent_30_Icu_SlowDataType (Short serial message)	24
Table 6-3	Sent_30_Icu_SlowDataType (Enhanced serial message).....	25
Table 6-4	Sent_30_Icu global variables.....	25
Table 6-5	Sent_30_Icu_Init.....	26
Table 6-6	Sent_30_Icu_DeInit	26
Table 6-7	Sent_30_Icu_IcuChannelCallback	26
Table 6-8	Sent_30_Icu_MainFunction	27
Table 6-9	Sent_30_Icu_GetVersionInfo	27
Table 6-10	Sent_30_Icu_GetFastChannelData	28
Table 6-11	Sent_30_Icu_GetSlowChannelData	28
Table 6-12	Sent_30_Icu_GetDiagnosticValues.....	29
Table 6-13	Sent_30_Icu_ResetDiagnosticValues	29
Table 7-1	Glossary	30
Table 7-2	Abbreviations.....	30

1 Component History

The component history gives an overview over the important milestones that are supported in the different versions of the component.

Component Version	New Features
[01.00.02]	Version ready for project release
[01.00.03]	Added notification functions and APIs for requesting SENT data

Table 1-1 Component history

2 Introduction

This document describes the functionality, API and configuration of the AUTOSAR BSW module Sent_30_Icu.

Supported AUTOSAR Release*:	3.X, 4.X	
Supported Configuration Variants:	<pre-compile>	
Vendor ID:	SENT_30_ICU_VENDOR_ID	30 decimal (= Vector-Informatik, according to HIS)
Module ID:	SENT_30_ICU_MODULE_ID	0x8001 decimal

* For the detailed functional specification please also refer to the corresponding AUTOSAR SWS.

The SENT (Single Edge Nibble Transmission) protocol is a non-expensive solution for transmitting sensor data to the ECU. It requires 3 wires: VCC, GND and SIG.

SENT data is transmitted in 4 bit units (= 1 nibble). The nibble data values are dependent on the interval between two falling edges on the SIG line. Each SENT frame consists of:

- > 1 calibration pulse to normalize the following pulses
- > 1 communication nibble for application data/slow channel messages
- > X data nibbles
- > 1 CRC nibble
- > (1 optional pause pulse)

The software component Sent_30_Icu is a handler for providing this SENT sensor data to the application layer.

2.1 Architecture Overview

The following figure shows where the Sent_30_Icu is located in the AUTOSAR architecture.




Figure 2-1 AUTOSAR 4.2 Architecture Overview




Figure 2-2 AUTOSAR 3.x Architecture Overview

The next figure shows the interfaces to adjacent modules of the Sent_30_Icu. These interfaces are described in chapter 6.




Figure 2-3 Interfaces to adjacent modules of the Sent_30_Icu

3 Functional Description

3.1 Use cases

The following use cases have been defined for the Sent_30_Icu:




Figure 3-1 Defined Use-cases for the Sent_30_Icu

3.2 Features

The Sent_30_Icu component provides the following features:

- > Support for one single SENT channel
- > Provides SENT sensor data to the application layer
- > Pre-compile time configuration to support any SENT sensor mode (variable tick times, data nibbles, pause pulse on/off)
- > Support for short serial messages and enhanced serial messages
- > Two different processing modes: MainFunction and IcuCallback
- > Checks 4Bit-CRC and 6Bit-CRC of messages

3.3 Limitations

The Sent_30_Icu doesn't support ECU to sensor communication.

The component provides only the raw sensor data without metadata and doesn't align this data depending on the sensor data format (e.g. A1, A.3, H.3). This has to be done by the application.

To see the test cases for this release, see [3].

3.4 Required knowledge

The component measures falling edges of the SENT channel by ICU timestamping. It creates a delta between two timestamps to get the actual pulse length. The pulse length is then evaluated and stored. Once all pulses of a frame are received, the frame will be validated and (if configured) the slow channel nibble is further evaluated.




Figure 3-2 Typical SENT frame (see [1]) – the nibble values are dependent on the delta between falling edges



Caution

The Sent_30_Icu is a highly timing dependent component and therefore it's important to correctly configure the tick times depending on the ECU and SENT sensor or else the calibration pulses won't be detected. Once the calibration pulses are within detection range, further pulses will be normalized to this pulse length and the receiving should work.

The SENT protocol specifies also so called serial messages (further referenced as slow channel messages). Such messages are transferred via 2 bits of the "Status & Communication"-nibble (the other 2 bits are reserved for sensor specific application usage). Every 2 bits of slow-channel data requires one fast-channel frame. Therefore, for one slow-channel frame, a number of successive fast-channel frames (without any errors) are required:

- > 16 for a short serial message
- > 18 for an enhanced serial message

3.5 Behavior

3.5.1 Initialization

The initialization function of the Sent_30_Icu pre-calculates timing thresholds (to save time in further cyclic function calls) and also starts the ICU timestamping. It also starts the state machines and sets the module to initialized.

3.5.2 Processing of timestamps

The component can be configured to use either a cyclic mainfunction or the ICU callback notification to process the measured timestamps.



Note

The more efficient process mode depends on whether slow-channel messages are used or not. Slow-channel messages require several successive fast-channel messages to be successfully received. Therefore it's recommended to use the callback method, because this ensures that no timestamp is missed.

When using the mainfunction method, the ICU-Buffer has to be large enough that in between two calls the ICU doesn't overwrite unprocessed stamps (resulting in a very large buffer – $256 \cdot 16 \text{uint16}$ for 10ms cycle time recommended = 4kB RAM).

3.5.2.1 MainFunction




Figure 3-3 MainFunction processing

The mainfunction iterates over all timestamp indexes which haven't been processed since the last function call. Each delta is then separately processed and, upon a complete message, written to a global.

3.5.2.2 IcuCallback




Figure 3-4 ICU callback processing

Each callback processes exactly one delta between the last timestamp and the current timestamp and feeds the length into the fast channel function.

3.5.3 Fast channel processing




Figure 3-5 Fast channel process

The fast channel process checks incoming pulse lengths, if they are within the configured threshold. Once a calibration pulse is detected, a correction factor is stored for the remaining pulses of the frame and the state is switched.

On successive calls, the pulses are then normalized and converted to actual data values. Once all nibbles of the frame have been received, the 4Bit CRC is checked. On correct CRC checksum, a positive return value is given.

3.5.4 Slow channel processing




Figure 3-6 Slow channel process

The slow-channel processing will only happen when a fast-channel message has been successfully received and a serial message is configured. The status bits are fed into the state machine and upon a complete message, the data will be written to the global variable.

The state machine and slow channel pulse processing differs depending on whether a Short-Serial-Message or an Enhanced-Serial-Message protocol is used.

3.6 Error Handling

3.6.1 Development Error Reporting

By default, development errors are reported to the DET using the service `Det_ReportError()` as specified in [5], if development error reporting is enabled (i.e. pre-compile parameter `SENT_30_ICU_DEV_ERROR_DETECT==STD_ON`).

If another module is used for development error reporting, the function prototype for reporting the error can be configured by the integrator, but must have the same signature as the service `Det_ReportError()`.

The reported Sent_30_Icu ID is 0x8001.

The reported service IDs identify the services which are described in Table 3-2. The following table presents the service IDs and the related services:

Service ID	Service
[0x00]	[Sent_30_Icu_Init]
[0x01]	[Sent_30_Icu_DeInit]
[0x02]	[Sent_30_Icu_IcuChannelCallback]
[0x03]	[Sent_30_Icu_MainFunction]
[0x04]	[Sent_30_Icu_GetVersionInfo]
[0x05]	[Sent_30_Icu_GetFastChannelData]
[0x06]	[Sent_30_Icu_GetSlowChannelData]

Table 3-1 Service IDs

The errors reported to DET are described in the following table:

Error Code	Description
[0x00]	Invalid pointer: an invalid pointer (NULL_PTR) was given
[0x01]	Function was called with uninitialized component
[0x02]	The component is already initialized
[0x03]	Invalid configuration parameter: Slow channel mode
[0x04]	Invalid configuration parameter: Tick time
[0x05]	Invalid configuration parameter: CPU tick time
[0x06]	Invalid configuration parameter: Data nibbles

Table 3-2 Errors reported to DET

4 Integration

This chapter gives necessary information for the integration of the Sent_30_Icu into an application environment of an ECU.

4.1 Scope of Delivery

The delivery of the Sent_30_Icu contains the following static files:

File Name	Description
Sent_30_Icu.c	This is the source file of the component.
Sent_30_Icu.h	This is the header file of the component.
Sent_30_Icu_Cfg.h	This is the header file of the precompile configuration module.

Table 4-1 Static files

Modifications should only be made in the precompile configuration module.

4.2 Required components

The Sent_30_Icu requires the following MICROSAR components:

Module	Description
ICU	Measures timestamps of falling edges on the SENT SIG line.
(DET)	Optional. Reports development errors.

Table 4-2 Required components

4.3 Initialization

To initialize the component in the ECU environment, the following functions have to be called (in this order):

- > Sent_30_Icu_InitMemory(void)
- > Sent_30_Icu_Init(void)

4.4 Operation

To operate in MainFunction mode, the Sent_30_Icu_MainFunction has to be called periodically. A detailed description of this function can be seen in [\[3.5.2.1\]](#).



Note

The Sent_30_E52141 was hardware tested with a cycle time of 10ms.

In IcuCallback mode, the notification function will be automatically called after each measure, if configured correctly.

4.5 Deinitialization

To turn the component off, the `Sent_30_Icu_DeInit` function can be called. This stops the ICU timestamping and the state machine.



Note

The component can be started again by calling `Sent_30_Icu_Init`.

5 Configuration

In the Sent_30_Icu driver, the attributes can only be configured PRE-COMPILE-TIME.

5.1 MICROSAR configuration

The component requires a configuration of the MICROSAR components. The configuration can be done with the Vector DaVinci Configurator tool.

5.1.1 ICU

The component needs one IcuChannel with the following attributes:

Attribute name	Attribute
Channel Id	ECU dependent (e.g. 1)
Hw Channel	ECU dependent (e.g. EMIOS_0_CH_1)
Emios Freeze	false
Emios Prescaler	ECU dependent (e.g. EMIOS_PRESCALER_DIVIDE_1)
Emios Digital Filter	EMIOS_DIGITAL_FILTER_BYPASSED
Emios Bus Select	EMIOS_BUS_INTERNAL_COUNTER
Measurement Mode	ICU_MODE_TIMESTAMP
Default Start Edge	ICU_FALLING_EDGE
Timestamp	ICU_CIRCULAR_BUFFER
Timestamp Notification	NULL_PTR (MainFunction mode) / Sent_30_Icu_IcuChannelCallback (Callback mode)
Dma Max. Channel	1 (recommended)
Ext. ISR IFCPR Digital Filter	0
Unused Wakeup Pins Pull Up	false
DMA enable	true (recommended)
Disable Ecum Wakeup Notification	false

Table 5-1 IcuChannel configuration



Note

DMA is recommended to enhance the performance of the component. Note that the DMA channel also has to be configured in **Mcu/McuModuleConfiguration/McuDMA/-emioschannel-**

Without DMA, a complete slow channel frame receive will be very unlikely!

5.1.2 PORT

Port access to the SENT SIG line must be configured:

Attribute name	Attribute
Pin PCR	ECU dependent (e.g. 1)
Mode	eMIOS_xxxx (e.g. E0UC1)
Level Value	PortPinLevelLow
Pin Slew Rate	Slow
Direction Changeable	false

Table 5-2 PORT attributes for the sent input

5.2 Configuration with the supplied configuration module

The component ships with a module template to configure the component as easily as possible.

5.2.1 Header file

Only the following defines should be modified:

Sent_30_Icu Configuration Items : Sent_30_Icu_Cfg.h	
Configuration Item	Description
SENT_30_ICU_DEV_ERROR_DETECT	Activates / deactivates support for DET. <i>STD_OFF</i> : The component does not use DET. <i>STD_ON</i> : The component uses the DET.
SENT_30_ICU_VERSION_INFO_API	Enables / disables the GetVersionInfo API. <i>STD_OFF</i> : The component offers the service. <i>STD_ON</i> : The component doesn't offer the service.
SENT_30_ICU_TIMER_CLOCK_UC_TICKS	Amount of ICU timer ticks per us.
SENT_30_ICU_TICK_TIME	SENT protocol tick time (found in sensor specification)
SENT_30_ICU_AMOUNT_OF_DATA_NIBBLES	Amount of data nibbles without calibration, CRC and status (found in sensor specification)
SENT_30_ICU_PAUSE_PULSE	Defines if a pause pulse is sent (found in sensor specification) <i>STD_OFF</i> : No pause pulse <i>STD_ON</i> : Pause pulse
SENT_30_ICU_SERIAL_FORMAT	Type of serial(slow) message used by the sensor (found in the sensor specification) <i>SENT_30_ICU_NO_SERIAL_MESSAGE</i> : No serial message used <i>SENT_30_ICU_SHORT_SERIAL_MESSAGE</i> : Short serial message format used. <i>SENT_30_ICU_ENHANCED_SERIAL_MESSAGE</i> : Enhanced serial message format used.

SENT_30_ICU_CHANNEL	Configured IcuChannel for timestamping.
SENT_30_ICU_USE_MAINFUNCTION	Defines the pulse processing mode. <i>STD_OFF</i> : IcuCallback notification is used <i>STD_ON</i> : Cyclic mainfunction is used
SENT_30_ICU_CALIB_THRESH_PERCENT	Defines the percentage maximum deviation from the calculated tick times. (SENT specification: 20%) <i>0-100u</i>
SENT_30_ICU_ENABLE_DIAGNOSIS	Defines if the diagnostic information APIs shall be available <i>STD_OFF</i> : No diagnostic data collection and API <i>STD_ON</i> : Diagnostic data will be collected and APIs are available
SENT_30_ICU_USE_NOTIFICATION	Defines if notification functions shall be called upon receiving a complete message <i>STD_OFF</i> : No notification call will be made <i>STD_ON</i> : Notification will be called upon a successful receive
SENT_30_ICU_NOTIFICATION_FUNC_FASTCH	Defines the function to be called upon receiving a complete fast channel message.
SENT_30_ICU_NOTIFICATION_FUNC_SLOWCH	Defines the function to be called upon receiving a complete slow channel message.

Table 5-3 Sent_30_Icu_Cfg.h configuration items

**Practical Procedure**

SENT_30_ICU_TIMER_CLOCK_UC_TICKS can be derived from the MCU settings.

An example (VC54S):

The core clock reference point frequency is 120Mhz

The periphral prescaler is 2

The eMIOS prescaler is 4

$120\text{Mhz} / 2 / 4 = 15\text{Mhz}$

$15\text{Mhz} \wedge = 15 \text{ ticks per us}$

**Practical Procedure**

While the SENT specification suggests a maximum deviation of 20%, depending on the sensor, it may be required to increase the define

SENT_30_ICU_CALIB_THRESH_PERCENT

or else no calibration pulses will be detected.

6 API Description

For an interfaces overview please see Figure 2-3.

6.1 Type Definitions

The types defined by the Sent_30_Icu are described in this chapter.

Sent_30_Icu_FastDataType

This structure is used as memory to store slow channel data when using the short serial message format.

Struct Element Name	C-Type	Description	Value Range
FastData	uint32	Memory type to store data from SENT fast channel. (Data[0] = LSB)	0x00000000 - 0xFFFFFFFF
StatusNibble	uint8	Contains the status nibble of the frame	0x00 - 0xFF

Table 6-1 Sent_30_Icu_FastDataType

Sent_30_Icu_SlowDataType (Short serial message)

This structure is used as memory to store slow channel data when using the short serial message format.

Struct Element Name	C-Type	Description	Value Range
Data	uint8	Contains the serial message data.	0x00 - 0xFF
MsgId	uint8	Contains the serial message identifier.	0x00 - 0xFF

Table 6-2 Sent_30_Icu_SlowDataType (Short serial message)

Sent_30_Icu_SlowDataType (Enhanced serial message)

This structure is used as memory to store slow channel data when using the enhanced serial message format. The actual data sizes depend on a so called configuration bit sent with every by the sensor.

Struct Element Name	C-Type	Description	Value Range
Data	uint16	Contains the serial message data.	0x0000 - 0xFF
MsgId	uint8	Contains the serial message identifier.	0x00 - 0xFF

Table 6-3 Sent_30_Icu_SlowDataType (Enhanced serial message)

The following tables describe the provided services of the Sent_30_Icu:

6.2 Global variables

Name	Type	Description
Sent_30_Icu_FastChannelData	Sent_30_Icu_FastChannelDataType	Contains the fast channel data from the SENT sensor.
Sent_30_Icu_SlowChannelData	Sent_30_Icu_SlowChannelDataType	Contains the slow channel data from the SENT sensor. (Only if serial message is configured)

Table 6-4 Sent_30_Icu global variables

6.3 Sent_30_Icu_Init

Prototype	
<code>void Sent_30_Icu_Init(void)</code>	
Parameter	
-	-
Return code	
-	-
Functional Description	
Performs the initialization described in [3.5.1] . It calculates thresholds to save time in future function calls and configures the ICU to start timestamping. It then sets the module status to initialized.	
Particularities and Limitations	
<p>> The component must be uninitialized</p>	

Call context

- > System initialization

Table 6-5 Sent_30_Icu_Init

6.4 Sent_30_Icu_DeInit

Prototype

```
void Sent_30_Icu_DeInit(void)
```

Parameter

-	-
---	---

Return code

-	-
---	---

Functional Description

This function deinitializes the module Sent_30_Icu. It stops the ICU timestamping and the state machine.

Particularities and Limitations

- > The module must be initialized

Call context

- > System shutdown / resource management

Table 6-6 Sent_30_Icu_DeInit

6.5 Sent_30_Icu_IcuChannelCallback

Prototype

```
void Sent_30_Icu_IcuChannelCallback(void)
```

Parameter

-	-
---	---

Return code

-	-
---	---

Functional Description

The callback function creates a delta from the last and current ICU timestamp and processes the pulse length. More details in [\[3.5.2.2\]](#).

Particularities and Limitations

- > The module must be initialized
- > The module must be configured in callback-mode

Call context

- > On every falling edge on SENT_IN by the ICU

Table 6-7 Sent_30_Icu_IcuChannelCallback

6.6 Sent_30_Icu_MainFunction

Prototype	
<code>void Sent_30_Icu_MainFunction(void)</code>	
Parameter	
-	-
Return code	
-	-
Functional Description	
This function iterates over all new timestamps since the last call and processes them. More details in [3.5.2.1] .	
Particularities and Limitations	
> The module must be initialized	
Call context	
> Cyclic (e.g. 10ms)	

Table 6-8 Sent_30_Icu_MainFunction

6.7 Sent_30_Icu_GetVersionInfo

Prototype	
<code>void Sent_30_Icu_GetVersionInfo(Std_VersionInfoType* versioninfo)</code>	
Parameter	
versioninfo	Pointer to type to store the module version info.
Return code	
-	-
Functional Description	
Requests module version information.	
Particularities and Limitations	
Call context	
> Application	

Table 6-9 Sent_30_Icu_GetVersionInfo

6.8 Sent_30_Icu_GetFastChannelData

Prototype	
<code>void Sent_30_Icu_GetFastChannelData (Sent_30_Icu_FastDataType* DataPtr)</code>	

Parameter	
DataPtr	Location where to store the data
Return code	
-	-
Functional Description	
Sent_30_Icu_GetFastChannelData writes the last successfully received fast channel data (raw data + status nibble) of the SENT channel to the pointer location.	
Particularities and Limitations	
> The module must be initialized	
Call context	
> Application	

Table 6-10 Sent_30_Icu_GetFastChannelData

6.9 Sent_30_Icu_GetSlowChannelData

Prototype	
void Sent_30_Icu_GetSlowChannelData (Sent_30_Icu_SlowDataType* DataPtr)	
Parameter	
DataPtr	Location where to store the data
Return code	
-	-
Functional Description	
Sent_30_Icu_GetSlowChannelData writes the last successfully received slow serial channel data of the SENT channel to the pointer location.	
Particularities and Limitations	
> The module must be initialized	
> Call context	
> Application	

Table 6-11 Sent_30_Icu_GetSlowChannelData

6.10 Sent_30_Icu_GetDiagnosticValues

Prototype	
void Sent_30_Icu_GetDiagnosticValues (Sent_30_Icu_DiagDataType* DataPtr)	
Parameter	
DataPtr	Location where to store the data
Return code	
-	-

Functional Description
The function writes the current collected diagnostic data values to the given location.
Particularities and Limitations
> The module must be initialized
Call context
> Application

Table 6-12 Sent_30_Icu_GetDiagnosticValues

6.11 Sent_30_Icu_ResetDiagnosticValues

Prototype
void Sent_30_Icu_ResetDiagnosticValues (void)
Parameter
-
Return code
-
Functional Description
The function resets the diagnostic counter values to 0.
Particularities and Limitations
> The module must be initialized
Call context
> Application

Table 6-13 Sent_30_Icu_ResetDiagnosticValues

7 Glossary and Abbreviations

7.1 Glossary

Term	Description

Table 7-1 Glossary

7.2 Abbreviations

Abbreviation	Description
API	Application Programming Interface
AUTOSAR	Automotive Open System Architecture
BSW	Basis Software
DET	Development Error Tracer
ECU	Electronic Control Unit
MICROSAR	Microcontroller Open System Architecture (the Vector AUTOSAR solution)
SWC	Software Component
SWS	Software Specification
ICU	Input capture unit
SENT	Single Edge Nibble Transmission

Table 7-2 Abbreviations

8 Contact

Visit our website for more information on

- > News
- > Products
- > Demo software
- > Support
- > Training data
- > Addresses

www.vector.com